

Yamaha USB-MIDI Driver for Windows2000/XP



Device Name : MOTIF-RACK ES

midi out

pc out

	1	2	3	4
OUT 1	↑	↑	↑	↑
OUT 2				
OUT 3				
OUT 4				

midi in

pc in

	1			
IN 1	↓	↓	↓	↓
IN				
IN				
IN				

midi in

midi out

	1			
1	↓	↓	↓	↓
2				
3				
4				

☒ Use Device Name As Port Name [Valid after system restart.]

☐ Thru ON/OFF




Yamaha USB-MIDI Driver for
Windows2000/XP Version 2.2.4
Copyright(C) 2003-2009 Yamaha Corporation
All Rights Reserved.

Send All Note OFF

Send All Note ON

OK

Cancel





MIDI-Anschluss-Einstellungen

Geräte

- Fernbedienungsgeräte
 - Quick Controls
 - Steinberg CC121
- MIDI
 - MIDI-Anschluss-Einstellungen**
- Transport
 - Anzeige verbleibender Aufnahmezeit
 - Zeitanzeige
- Video
 - Video-Player
- VST-Audiosystem
 - MOTU Audio ASIO
- Studio Manager
- VST System Link

Gerät	E/A	Anschluss	Anzeigen als	Sichtbar	Status	In 'All MIDI In'
Windows MIDI	In	E-MU Xboard49	E-MU Xboard49	☒	Aktiv	☐
Windows MIDI	In	Lexicon MX400 Control	Lexicon MX400 Control	☐	Nicht aktiv	☐
Windows MIDI	In	Steinberg CC121-1	Steinberg CC121-1	☒	Aktiv	☐
Windows MIDI	In	Yamaha MOTIF-RACK ES-1	Yamaha MOTIF-RACK ES-1	☒	Aktiv	☐
Windows MIDI	In	Yamaha UX16-1	Yamaha UX16-1	☒	Aktiv	☐
Windows MIDI	Out	E-MU Xboard49	E-MU Xboard49	☒	Nicht aktiv	
Windows MIDI	Out	Lexicon MX400 Control	Lexicon MX400 Control	☐	Nicht aktiv	
Windows MIDI	Out	Steinberg CC121-1	Steinberg CC121-1	☒	Aktiv	
Windows MIDI	Out	Yamaha MOTIF-RACK ES-1	Yamaha MOTIF-RACK ES-1	☒	Aktiv	
Windows MIDI	Out	Yamaha MOTIF-RACK ES-2	Yamaha MOTIF-RACK ES-2	☒	Aktiv	
Windows MIDI	Out	Yamaha MOTIF-RACK ES-3	Yamaha MOTIF-RACK ES-3	☐	Nicht aktiv	
Windows MIDI	Out	Yamaha MOTIF-RACK ES-4	Yamaha MOTIF-RACK ES-4	☐	Nicht aktiv	
Windows MIDI	Out	Yamaha MOTIF-RACK ES-5	Yamaha MOTIF-RACK ES-5	☐	Nicht aktiv	
Windows MIDI	Out	Yamaha MOTIF-RACK ES-6	Yamaha MOTIF-RACK ES-6	☐	Nicht aktiv	
Windows MIDI	Out	Yamaha MOTIF-RACK ES-7	Yamaha MOTIF-RACK ES-7	☐	Nicht aktiv	
Windows MIDI	Out	Yamaha MOTIF-RACK ES-8	Yamaha MOTIF-RACK ES-8	☐	Nicht aktiv	
Windows MIDI	Out	Yamaha UX16-1	Yamaha UX16-1	☐	Nicht aktiv	

☒ Systemzeit verwenden für 'Windows MIDI'-Eingänge


Hilfe

Zurücksetzen

Übernehmen

OK

Abbrechen



Kein Objekt ausgewählt

DX7

E-MU Xboard49
Yamaha MO...RACK ES-2
2
Aus
Keine Drum-Map

Kein Spur-Preset

VST Expression
MIDI-Insert-Effekte
MIDI-Kanalzug
Notizen
Quick ControlsVST-Instrumente
MOTIF-RACK ES (Voice)
1
M S MOTIF-R...Voice) 1
R W Lautstärke 0.00MOTIF-RACK ES (Multi)
3
M S Kopie vo...oice) 03
R W 1
Yamaha MOTIF-RACK ES-1
Aus Aus4
M S DX7
R W 2
Yamaha MOTIF-RACK ES-2
Aus Aus5
M S MIDI 02
R W 2
MOTIF-RACK ES (Multi) Ya
Aus Aus6
M S Unbenannt2-03
stereo
Aus7
M S Unbenannt26 (2)
Aus

Aufn.: 88200 Hz - 24 Bit - Max: 65h 39min - 30 fps - Pan: Konst. Leistung

9 2 3 4 10 2 3 4 11 2 3

Kopie von MOTIF-RACK ES (Voice) 03

Kopie von MOTIF-RACK ES (Voice) 03

Runde1 MIDI 02

Unbenannt2-03

DX Simulator Setup



MIDI

Insert & Transmit

MIDI In

Yamaha MOTIF-RACK ES-1



MIDI Out

Yamaha MOTIF-RACK ES-2



MIDI CH

2



Board No.

1



Part No.

15



Device No.

15



Output when edited

OK

Abbrechen

Motif Rack ES Settings:

MIDI

- Basic rcv channel: 1
- Transmit ch:1
- Device No.: 16
- Bank Sel. Switch: on
- Pgm change switch: on
- CC Mode : Mode1
- RecBulkSwitch: on
- MIDI Sync: internal
- MIDI in /out : USB
- Through port: 1

PLG2 SYS

- Poly expand: off
- Device No. 15
- Port No. 2
- Rcv GM/XG: ---
- Bulk Block: 33-64
- Vel Curve: Normal